OVERVIEW PACKAGE CLASS USE TREE DEPRECATED INDEX HELP

PREV CLASS NEXT CLASS FRAMES NO FRAMES ALL CLASSES

SUMMARY: NESTED | FIELD | CONSTR | METHOD DETAIL: FIELD | CONSTR | METHOD

compact1, compact2, compact3 java.io

Class PrintWriter

java.lang.Object java.io.Writer java.io.PrintWriter

All Implemented Interfaces:

Closeable, Flushable, Appendable, AutoCloseable

public class PrintWriter
extends Writer

Prints formatted representations of objects to a text-output stream. This class implements all of the print methods found in PrintStream. It does not contain methods for writing raw bytes, for which a program should use unencoded byte streams.

Unlike the PrintStream class, if automatic flushing is enabled it will be done only when one of the println, printf, or format methods is invoked, rather than whenever a newline character happens to be output. These methods use the platform's own notion of line separator rather than the newline character.

Methods in this class never throw I/O exceptions, although some of its constructors may. The client may inquire as to whether any errors have occurred by invoking checkError().

Since:

JDK1.1

Field Summary

Fields

Modifier and Type Field and Description

protected Writer out

The underlying character-output stream of this PrintWriter.

Fields inherited from class java.io.Writer

lock

Constructor Summary

Constructors

Constructor and Description

PrintWriter(File file)

Creates a new PrintWriter, without automatic line flushing, with the specified file.

PrintWriter(File file, String csn)

Creates a new PrintWriter, without automatic line flushing, with the specified file and charset.

PrintWriter(OutputStream out)

Creates a new PrintWriter, without automatic line flushing, from an existing OutputStream.

PrintWriter(OutputStream out, boolean autoFlush)

Creates a new PrintWriter from an existing OutputStream.

PrintWriter(String fileName)

Creates a new PrintWriter, without automatic line flushing, with the specified file name.

PrintWriter(String fileName, String csn)

Creates a new PrintWriter, without automatic line flushing, with the specified file name and charset.

PrintWriter(Writer out)

Creates a new PrintWriter, without automatic line flushing.

PrintWriter(Writer out, boolean autoFlush)

Creates a new PrintWriter.

Method Summary

All Methods Inst	cance Methods Concrete Methods
Modifier and Type	Method and Description
PrintWriter	<pre>append(char c) Appends the specified character to this writer.</pre>
PrintWriter	<pre>append(CharSequence csq) Appends the specified character sequence to this writer.</pre>
PrintWriter	<pre>append(CharSequence csq, int start, int end) Appends a subsequence of the specified character sequence to this writer.</pre>

boolean checkError()

Flushes the stream if it's not closed and checks its error state.

Clears the error state of this stream.

void close()

Closes the stream and releases any system resources associated

with it.

void flush()

Flushes the stream.

PrintWriter format(Locale l, String format, Object... args)

Writes a formatted string to this writer using the specified format

string and arguments.

PrintWriter format(String format, Object... args)

Writes a formatted string to this writer using the specified format

string and arguments.

Prints a boolean value.

void print(char c)

Prints a character.

Prints an array of characters.

Prints a double-precision floating-point number.

Prints a floating-point number.

Prints an integer.

Prints a long integer.

Prints an object.

void print(String s)

Prints a string.

A convenience method to write a formatted string to this writer

using the specified format string and arguments.

A convenience method to write a formatted string to this writer

using the specified format string and arguments.

void println()

Terminates the current line by writing the line separator string.

Prints a boolean value and then terminates the line.

void println(char x)

Prints a character and then terminates the line.

void println(char[] x)

Prints an array of characters and then terminates the line.

Prints a double-precision floating-point number and then

terminates the line.

void println(float x)

Prints a floating-point number and then terminates the line.

void println(int x)

Prints an integer and then terminates the line.

void println(long x)

Prints a long integer and then terminates the line.

void println(Object x)

Prints an Object and then terminates the line.

void println(String x)

Prints a String and then terminates the line.

protected void setError()

Indicates that an error has occurred.

void write(char[] buf)

Writes an array of characters.

void write(char[] buf, int off, int len)

Writes A Portion of an array of characters.

void write(int c)

Writes a single character.

void write(String s)

Writes a string.

void write(String s, int off, int len)

Writes a portion of a string.

Methods inherited from class java.lang.Object

clone, equals, finalize, getClass, hashCode, notify, notifyAll, toString,
wait, wait

Field Detail

out

protected Writer out

The underlying character-output stream of this PrintWriter.

Since:

1.2

Constructor Detail

PrintWriter

public PrintWriter(Writer out)

Creates a new PrintWriter, without automatic line flushing.

Parameters:

out - A character-output stream

PrintWriter

Creates a new PrintWriter.

Parameters:

out - A character-output stream

autoFlush - A boolean; if true, the println, printf, or format methods will flush the output buffer

PrintWriter

public PrintWriter(OutputStream out)

Creates a new PrintWriter, without automatic line flushing, from an existing OutputStream. This convenience constructor creates the necessary intermediate OutputStreamWriter, which will convert characters into bytes using the default character encoding.

Parameters:

out - An output stream

See Also:

OutputStreamWriter.OutputStreamWriter(java.io.OutputStream)

PrintWriter

Creates a new PrintWriter from an existing OutputStream. This convenience constructor creates the necessary intermediate OutputStreamWriter, which will convert characters into bytes using the default character encoding.

Parameters:

out - An output stream

autoFlush - A boolean; if true, the println, printf, or format methods will flush the output buffer

See Also:

OutputStreamWriter.OutputStreamWriter(java.io.OutputStream)

PrintWriter

Creates a new PrintWriter, without automatic line flushing, with the specified file name. This convenience constructor creates the necessary intermediate OutputStreamWriter, which will encode characters using the default charset for this instance of the Java virtual machine.

Parameters:

fileName - The name of the file to use as the destination of this writer. If the file exists then it will be truncated to zero size; otherwise, a new file will be created. The output will be written to the file and is buffered.

Throws:

FileNotFoundException - If the given string does not denote an existing, writable regular file and a new regular file of that name cannot be created, or if some other error occurs while opening or creating the file

SecurityException - If a security manager is present and checkWrite(fileName) denies write access to the file

Since:

1.5

PrintWriter

Creates a new PrintWriter, without automatic line flushing, with the specified file name and charset. This convenience constructor creates the necessary intermediate OutputStreamWriter, which will encode characters using the provided charset.

Parameters:

fileName - The name of the file to use as the destination of this writer. If the file exists then it will be truncated to zero size; otherwise, a new file will be created. The output will be written to the file and is buffered.

csn - The name of a supported charset

Throws:

FileNotFoundException - If the given string does not denote an existing, writable regular file and a new regular file of that name cannot be created, or if some other error occurs while opening or creating the file

SecurityException - If a security manager is present and checkWrite(fileName) denies write access to the file

UnsupportedEncodingException - If the named charset is not supported

Since:

1.5

PrintWriter

Creates a new PrintWriter, without automatic line flushing, with the specified file. This convenience constructor creates the necessary intermediate OutputStreamWriter, which will encode characters using the default charset for this instance of the Java virtual machine.

Parameters:

file - The file to use as the destination of this writer. If the file exists then it will be truncated to zero size; otherwise, a new file will be created. The output will be written to the file and is buffered.

Throws:

FileNotFoundException - If the given file object does not denote an existing, writable regular file and a new regular file of that name cannot be created, or if some other error occurs while opening or creating the file

SecurityException - If a security manager is present and
checkWrite(file.getPath()) denies write access to the file

Since:

1.5

PrintWriter

Creates a new PrintWriter, without automatic line flushing, with the specified file and charset. This convenience constructor creates the necessary intermediate OutputStreamWriter, which will encode characters using the provided charset.

Parameters:

file - The file to use as the destination of this writer. If the file exists then it will be truncated to zero size; otherwise, a new file will be created. The output will be written to the file and is buffered.

csn - The name of a supported charset

Throws:

FileNotFoundException - If the given file object does not denote an existing, writable regular file and a new regular file of that name cannot be created, or if some other error occurs while opening or creating the file

SecurityException - If a security manager is present and
checkWrite(file.getPath()) denies write access to the file

UnsupportedEncodingException - If the named charset is not supported

Since:

1.5

Method Detail

flush

public void flush()

Flushes the stream.

Specified by:

flush in interface Flushable

Specified by:

flush in class Writer

See Also:

checkError()

close

public void close()

Closes the stream and releases any system resources associated with it. Closing a previously closed stream has no effect.

Specified by:

close in interface Closeable

Specified by:

close in interface AutoCloseable

Specified by:

close in class Writer

See Also:

checkError()

checkError

public boolean checkError()

Flushes the stream if it's not closed and checks its error state.

Returns:

true if the print stream has encountered an error, either on the underlying output stream or during a format conversion.

setError

protected void setError()

Indicates that an error has occurred.

This method will cause subsequent invocations of checkError() to return true until clearError() is invoked.

clearError

protected void clearError()

Clears the error state of this stream.

This method will cause subsequent invocations of checkError() to return false until another write operation fails and invokes setError().

Since:

1.6

write

public void write(int c)

Writes a single character.

Overrides:

write in class Writer

Parameters:

c - int specifying a character to be written.

write

Writes A Portion of an array of characters.

Specified by:

write in class Writer

Parameters:

buf - Array of characters

off - Offset from which to start writing characters

len - Number of characters to write

write

```
public void write(char[] buf)
```

Writes an array of characters. This method cannot be inherited from the Writer class because it must suppress I/O exceptions.

Overrides:

write in class Writer

Parameters:

buf - Array of characters to be written

write

Writes a portion of a string.

Overrides:

write in class Writer

Parameters:

s - A String

off - Offset from which to start writing characters

len - Number of characters to write

write

```
public void write(String s)
```

Writes a string. This method cannot be inherited from the Writer class because it must suppress I/O exceptions.

Overrides:

write in class Writer

Parameters:

s - String to be written

print

```
public void print(boolean b)
```

Prints a boolean value. The string produced by String.valueOf(boolean) is translated into bytes according to the platform's default character encoding, and these bytes are written in exactly the manner of the write(int) method.

Parameters:

b - The boolean to be printed

print

public void print(char c)

Prints a character. The character is translated into one or more bytes according to the platform's default character encoding, and these bytes are written in exactly the manner of the write(int) method.

Parameters:

c - The char to be printed

print

```
public void print(int i)
```

Prints an integer. The string produced by String.valueOf(int) is translated into bytes according to the platform's default character encoding, and these bytes are written in exactly the manner of the write(int) method.

Parameters:

i - The int to be printed

See Also:

Integer.toString(int)

print

```
public void print(long l)
```

Prints a long integer. The string produced by String.valueOf(long) is translated into bytes according to the platform's default character encoding, and these bytes are written in exactly the manner of the write(int) method.

Parameters:

l - The long to be printed

See Also:

Long.toString(long)

print

```
public void print(float f)
```

Prints a floating-point number. The string produced by String.valueOf(float) is translated into bytes according to the platform's default character encoding, and these bytes are written in exactly the manner of the write(int) method.

Parameters:

f - The float to be printed

See Also:

Float.toString(float)

print

public void print(double d)

Prints a double-precision floating-point number. The string produced by String.valueOf(double) is translated into bytes according to the platform's default character encoding, and these bytes are written in exactly the manner of the write(int) method.

Parameters:

d - The double to be printed

See Also:

Double.toString(double)

print

public void print(char[] s)

Prints an array of characters. The characters are converted into bytes according to the platform's default character encoding, and these bytes are written in exactly the manner of the write(int) method.

Parameters:

s - The array of chars to be printed

Throws:

NullPointerException - If s is null

print

public void print(String s)

Prints a string. If the argument is null then the string "null" is printed. Otherwise, the string's characters are converted into bytes according to the platform's default character encoding, and these bytes are written in exactly the manner of the write(int) method.

Parameters:

s - The String to be printed

print

public void print(Object obj)

Prints an object. The string produced by the String.valueOf(Object) method is translated into bytes according to the platform's default character encoding, and these bytes are written in exactly the manner of the write(int) method.

Parameters:

obj - The Object to be printed

See Also:

Object.toString()

println

```
public void println()
```

Terminates the current line by writing the line separator string. The line separator string is defined by the system property line.separator, and is not necessarily a single newline character (' \n').

println

```
public void println(boolean x)
```

Prints a boolean value and then terminates the line. This method behaves as though it invokes print(boolean) and then println().

Parameters:

x - the boolean value to be printed

println

```
public void println(char x)
```

Prints a character and then terminates the line. This method behaves as though it invokes print(char) and then println().

Parameters:

x - the char value to be printed

println

```
public void println(int x)
```

Prints an integer and then terminates the line. This method behaves as though it invokes print(int) and then println().

Parameters:

x - the int value to be printed

println

public void println(long x)

Prints a long integer and then terminates the line. This method behaves as though it invokes print(long) and then println().

Parameters:

x - the long value to be printed

println

```
public void println(float x)
```

Prints a floating-point number and then terminates the line. This method behaves as though it invokes print(float) and then println().

Parameters:

x - the float value to be printed

println

```
public void println(double x)
```

Prints a double-precision floating-point number and then terminates the line. This method behaves as though it invokes print(double) and then println().

Parameters:

x - the double value to be printed

println

```
public void println(char[] x)
```

Prints an array of characters and then terminates the line. This method behaves as though it invokes print(char[]) and then println().

Parameters:

x - the array of char values to be printed

println

```
public void println(String x)
```

Prints a String and then terminates the line. This method behaves as though it invokes print(String) and then println().

Parameters:

x - the String value to be printed

println

public void println(Object x)

Prints an Object and then terminates the line. This method calls at first String.valueOf(x) to get the printed object's string value, then behaves as though it invokes print(String) and then println().

Parameters:

x - The Object to be printed.

printf

A convenience method to write a formatted string to this writer using the specified format string and arguments. If automatic flushing is enabled, calls to this method will flush the output buffer.

An invocation of this method of the form out.printf(format, args) behaves in exactly the same way as the invocation

```
out.format(format, args)
```

Parameters:

format - A format string as described in Format string syntax.

args - Arguments referenced by the format specifiers in the format string. If there are more arguments than format specifiers, the extra arguments are ignored. The number of arguments is variable and may be zero. The maximum number of arguments is limited by the maximum dimension of a Java array as defined by *The Java™ Virtual Machine Specification*. The behaviour on a null argument depends on the conversion.

Returns:

This writer

Throws:

IllegalFormatException - If a format string contains an illegal syntax, a format specifier that is incompatible with the given arguments, insufficient arguments given the format string, or other illegal conditions. For specification of all possible formatting errors, see the Details section of the formatter class specification.

NullPointerException - If the format is null

Since:

1.5

printf

A convenience method to write a formatted string to this writer using the specified format string and arguments. If automatic flushing is enabled, calls to this method will flush the output buffer.

An invocation of this method of the form out.printf(l, format, args) behaves in exactly the same way as the invocation

```
out.format(l, format, args)
```

Parameters:

l - The locale to apply during formatting. If l is null then no localization
is applied.

format - A format string as described in Format string syntax.

args - Arguments referenced by the format specifiers in the format string. If there are more arguments than format specifiers, the extra arguments are ignored. The number of arguments is variable and may be zero. The maximum number of arguments is limited by the maximum dimension of a Java array as defined by *The Java™ Virtual Machine Specification*. The behaviour on a null argument depends on the conversion.

Returns:

This writer

Throws:

IllegalFormatException - If a format string contains an illegal syntax, a format specifier that is incompatible with the given arguments, insufficient arguments given the format string, or other illegal conditions. For specification of all possible formatting errors, see the Details section of the formatter class specification.

NullPointerException - If the format is null

Since:

1.5

format

Writes a formatted string to this writer using the specified format string and arguments. If automatic flushing is enabled, calls to this method will flush the output buffer.

The locale always used is the one returned by Locale.getDefault(), regardless of any previous invocations of other formatting methods on this object.

Parameters:

format - A format string as described in Format string syntax.

args - Arguments referenced by the format specifiers in the format string. If there are more arguments than format specifiers, the extra arguments are ignored. The number of arguments is variable and may be zero. The maximum number of arguments is limited by the maximum dimension of a Java array as defined by *The Java™ Virtual Machine Specification*. The behaviour on a null argument depends on the conversion.

Returns:

This writer

Throws:

IllegalFormatException - If a format string contains an illegal syntax, a format specifier that is incompatible with the given arguments, insufficient arguments given the format string, or other illegal conditions. For specification of all possible formatting errors, see the Details section of the Formatter class specification.

NullPointerException - If the format is null

Since:

1.5

format

Writes a formatted string to this writer using the specified format string and arguments. If automatic flushing is enabled, calls to this method will flush the output buffer.

Parameters:

l - The locale to apply during formatting. If l is null then no localization is applied.

format - A format string as described in Format string syntax.

args - Arguments referenced by the format specifiers in the format string. If there are more arguments than format specifiers, the extra arguments are ignored. The number of arguments is variable and may be zero. The maximum number of arguments is limited by the maximum dimension of a Java array as defined by *The Java™ Virtual Machine Specification*. The behaviour on a null argument depends on the conversion.

Returns:

This writer

Throws:

IllegalFormatException - If a format string contains an illegal syntax, a format specifier that is incompatible with the given arguments, insufficient arguments given the format string, or other illegal conditions. For specification of all possible formatting errors, see the Details section of the formatter class specification.

NullPointerException - If the format is null

Since:

1.5

append

public PrintWriter append(CharSequence csq)

Appends the specified character sequence to this writer.

An invocation of this method of the form out.append(csq) behaves in exactly the same way as the invocation

```
out.write(csq.toString())
```

Depending on the specification of toString for the character sequence csq, the entire sequence may not be appended. For instance, invoking the toString method of a character buffer will return a subsequence whose content depends upon the buffer's position and limit.

Specified by:

append in interface Appendable

Overrides:

append in class Writer

Parameters:

csq - The character sequence to append. If csq is null, then the four characters "null" are appended to this writer.

Returns:

This writer

Since:

1.5

append

int end)

Appends a subsequence of the specified character sequence to this writer.

An invocation of this method of the form out.append(csq, start, end) when csq is not null, behaves in exactly the same way as the invocation

out.write(csq.subSequence(start, end).toString())

Specified by:

append in interface Appendable

Overrides:

append in class Writer

Parameters:

csq - The character sequence from which a subsequence will be appended. If csq is null, then characters will be appended as if csq contained the four characters "null".

start - The index of the first character in the subsequence

end - The index of the character following the last character in the subsequence

Returns:

This writer

Throws:

IndexOutOfBoundsException - If start or end are negative, start is greater
than end, or end is greater than csq.length()

Since:

1.5

append

public PrintWriter append(char c)

Appends the specified character to this writer.

An invocation of this method of the form out.append(c) behaves in exactly the same way as the invocation

out.write(c)

Specified by:

append in interface Appendable

Overrides:

append in class Writer

Parameters:

c - The 16-bit character to append

Returns:

This writer

Since:

1.5

Java™ Platform Standard Ed. 8

OVERVIEW PACKAGE CLASS USE TREE DEPRECATED INDEX HELP

PREV CLASS NEXT CLASS FRAMES NO FRAMES ALL CLASSES

SUMMARY: NESTED | FIELD | CONSTR | METHOD | DETAIL: FIELD | CONSTR | METHOD

Submit a bug or feature

For further API reference and developer documentation, see Java SE Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.

Copyright © 1993, 2024, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms. Also see the documentation redistribution policy. Modify Preferencias sobre cookies. Modify Ad Choices.